
HOWNER_OPERATOR2

English Name EPA Handler ID **(Primary Key)**
Description Unique RCRA identification number assigned by the implementing State or Region to each RCRA site (e.g., generators; transporters; and treatment, storage, disposal facilities).
Data Type and Length CHAR (12)
Allowed Values Valid ID as outlined below:
 The ID can be a minimum of 4 characters and a maximum of 12 characters.
 The first two characters must be a valid state postal code which corresponds to the state in which the handler is located.
 Spaces are not allowed.
Default Value
Notes Handlers associated with Navajo Nation should be assigned Handler IDs beginning with "NN" regardless of where the handler is physically located.

English Name Activity Location **(Primary Key)**
Description Indicates the location of the agency regulating the handler.
Data Type and Length CHAR (2)
Allowed Values State postal code
Default Value Location associated with the current user ID.
Notes For a list of valid state postal codes, refer to the Column Information Report for LU_STATE.

English Name Source Type **(Primary Key)**
Description Code indicating the source of information for the associated data (activity, wastes, etc.).
Data Type and Length CHAR (1)
Allowed Values

A	Part A
B	Annual/Biennial Report updated with Notification
E	Emergency
I	Implementer
N	Notification
R	Annual/Biennial Report
T	Temporary

Default Value

English Name Handler Sequence Number **(Primary Key)**
Description Sequence number for each source record about a handler.
Data Type and Length NUMBER (6.0)
Allowed Values 1 - 999999
Default Value

HOWNER_OPERATOR2

English Name	Owner/Operator Sequence Number (Primary Key)	
Description	Sequential number used to order multiple occurrences of owners and operators.	
Data Type and Length	NUMBER (4.0)	
Allowed Values	1 - 9999	
Default Value		
Notes	This number will be incremented by one for each Add transaction.	
English Name	Owner/Operator Indicator	
Description	Code indicating whether the data is associated with a current or previous owner or operator. The system will allow multiple current owners and operators.	
Data Type and Length	CHAR (2)	
Allowed Values	CO	Current owner
	CP	Current operator
Default Value		
English Name	Owner/Operator Name	
Description	Owner Name: The name of the entity (individual, agency, corporation) having legal ownership of the physical operation. The owner name may or may not be the same as the actual site name or the operator name.	
	Operator Name: The name of the entity (individual, agency, corporation) that is responsible for the overall operation of the facility. The operator name may or may not be the same as the actual site name or the owner name.	
Data Type and Length	VARCHAR2 (40)	
Allowed Values	Any non-blank value	
Default Value		
English Name	Owner/Operator Type	
Description	Owner Type: Code indicating the type of entity that legally owns the facility.	
	Operator Type: Code indicating the type of entity that is responsible for the overall operation of the facility.	
Data Type and Length	CHAR (1)	
Allowed Values	C	County
	D	District
	F	Federal
	I	Indian
	M	Municipal
	O	Other
	P	Private
	S	State
Default Value		

HOWNER_OPERATOR2

English Name Date Became Current
Description Date indicating when the owner/operator became current.
Data Type and Length DATE
Allowed Values Valid date in MM/DD/YYYY format
Default Value

English Name Date Ended Current
Description Date indicating when the owner/operator changed to a different owner/operator.
Data Type and Length DATE
Allowed Values Valid date in MM/DD/YYYY format
blank Not provided
Default Value blank
Notes When entering a new owner/operator, any previous owners/operators that are no longer current should be updated to include a Date Ended Current.

English Name Owner/Operator Street 1
Description First line of the street address or post office box number of the facility owner or operator.
Data Type and Length VARCHAR2 (30)
Allowed Values Any value
blank Not provided
Default Value blank

English Name Owner/Operator Street 2
Description Second line of the street address or post office box number of the facility owner or operator.
Data Type and Length VARCHAR2 (30)
Allowed Values Any value
blank Not provided
Default Value blank

HOWNER_OPERATOR2

English Name Owner/Operator City
Description The city or town in the address of the facility owner or operator.
Data Type and Length VARCHAR2 (25)
Allowed Values Any value
 blank Not provided
Default Value blank

English Name Owner/Operator State
Description The two-letter postal code for the state in the address of the facility owner or operator.
Data Type and Length CHAR (2)
Allowed Values Valid state postal code
Default Value
Notes For a list of valid state postal codes, refer to the Column Information Report for LU_STATE.

English Name Owner/Operator Country
Description The country code for the address of the facility owner or operator.
Data Type and Length CHAR (2)
Allowed Values For a complete list of valid country codes, refer to: <http://www.bcpl.net/~j1m5path/isocodes.html>.
 Valid country code
Default Value US - United States

English Name Owner/Operator Zip Code
Description Zip code in the address of the owner or operator.
Data Type and Length VARCHAR2 (14)
Allowed Values Any value
 blank Not provided
Default Value blank

HOWNER_OPERATOR2

English Name	Owner/Operator Phone
Description	Telephone number associated with the owner or operator.
Data Type and Length	VARCHAR2 (15)
Allowed Values	Any value blank Not provided
Default Value	blank
Notes	Telephone number can include space, parentheses and hyphen.
English Name	Dunn & Bradstreet Number
Description	Nine-digit unique identification number assigned by the Dunn & Bradstreet organization to a company that might own or operate a site. The identifier serves as linkage for commercially available information pertaining to the site.
Data Type and Length	VARCHAR2 (10)
Allowed Values	Any value blank Not provided
Default Value	blank
English Name	Owner/Operator Street Number
Description	The street number from the address of the facility owner or operator.
Data Type and Length	VARCHAR2 (12)
Allowed Values	Any value blank Not provided
Default Value	blank
English Name	User ID of Last Change
Description	Records the user ID of the last person to change the data.
Data Type and Length	VARCHAR2 (6)
Allowed Values	Valid user ID
Default Value	Current user ID

HOWNER_OPERATOR2

English Name	Date of Last Change
Description	Records the date that the data was last changed.
Data Type and Length	DATE
Allowed Values	Valid date/time stamp
Default Value	Current date and time

English Name	Notes
Description	Additional information regarding the owner/operator.
Data Type and Length	VARCHAR2 (240)
Allowed Values	Any value blank Not provided
Default Value	blank

*** End of Report ***