	· · · · · · · · · · · · · · · · · · ·	
HOWNER_OPERATOR5		
Business Rules	<ul> <li>User must be the implementer of record for Handler information.</li> <li>Handler ID, Activity Location, Source Type, and Sequence Number must exist in HHANDLER5.</li> <li>Handler ID, Activity Location, Source Type, Sequence Number, and Owner/Operator Sequence Number must be unique.</li> <li>Use of the HOWNER_OPERATOR5 table is mandatory.</li> </ul>	
English Name Description	EPA Handler ID ( <b>Primary Key</b> ) Unique RCRA identification number assigned by the implementing State or Region to each RCRA site (e.g., generators; transporters; and treatment, storage, disposal facilities).	
Data Type and Length Allowed Values	VARCHAR2 (12) Valid ID as outlined below: The ID can be a minimum of 4 characters and a maximum of 12 characters. The first two characters must be a valid state postal code which corresponds to the state in which the handler is located. Spaces are not allowed.	
Default Value Notes	Handlers associated with Navajo Nation should be assigned Handler IDs beginning with 'NN' regardless of where the handler is physically located.	
English Name Description Data Type and Length Allowed Values Default Value Notes	Activity Location (Primary Key) Indicates the location of the agency regulating the handler. CHAR (2) State postal code Location associated with the current user ID. For a list of valid state postal codes, refer to the Column Information Report for LU_STATE.	
English Name Description Data Type and Length Allowed Values	Source Type (Primary Key) Code indicating the source of information for the associated data (activity, wastes, etc.).  CHAR (1)  A Part A  B Annual/Biennial Report updated with Notification  E Emergency I Implementer N Notification R Annual/Biennial Report T Temporary	
Default Value Notes	If the BR Report Cycle >= 2009 then the Source Type must equal 'B'.	
English Name Description Data Type and Length	Handler Sequence Number (Primary Key) Sequence number for each source record about a handler. NUMBER (6.0)	

HOWNER_OPERATOR5		
Allowed Values Default Value	1 - 999999	
English Name Description Data Type and Length Allowed Values Default Value	Owner/Operator Sequence Number (Primary Key) Sequential number used to order multiple occurrences of owners and operators. NUMBER (4.0) 1 - 9999	
English Name Description	Owner/Operator Indicator Code indicating whether the data is associated with a current or previous owner or operator. The system will allow multiple current owners and operators.	
Data Type and Length Allowed Values	CHAR (2) CO Current owner CP Current operator PO Previous owner PP Previous operator	
Default Value Notes	If the Receive Date >= 1/1/2004 then the Owner/Operator Indicator cannot equal 'PO' - Previous owner or 'PP' - Previous operator.	
English Name Description	Owner/Operator Type Owner Type: Code indicating the type of entity that legally owns the facility.	
Data Type and Length Allowed Values	Operator Type: Code indicating the type of entity that is responsible for the overall operation of the facility.  CHAR (1)  County  District  Federal  ITribal  Municipal  Other  Private  State	
Default Value		

## **HOWNER OPERATOR5**

**English Name** 

Owner/Operator Name

Description

Owner Name: The name of the entity (individual, agency, or corporation) having legal ownership of the physical operation. The owner name may or may not be the same as the actual site name or the operator name.

Operator Name: The name of the entity (individual, agency, or corporation) that is responsible for the overall operation of the facility. The operator name may or may not be the same as the actual site name or the owner name.

Data Type and Length VARCHAR2 (40)

Any non-blank value

**Allowed Values Default Value** 

**Date Became Current English Name** 

Date indicating when the owner/operator became current. Description

Data Type and Length DATE

**Allowed Values** Valid date greater than or equal to January 1, 1600 in MM/DD/YYYY format

> Not provided blank

**Default Value** blank

If the Receive Date >= 1/1/2004 then the Date Became Current must be provided. Notes

**Date Ended Current English Name** 

Description Date indicating when the owner/operator changed to a different owner/operator.

Data Type and Length DATE

Allowed Values Valid date greater than or equal to the Date Became Current in MM/DD/YYYY format

blank Not provided

**Default Value** blank

When entering a new owner/operator, any previous owners/operators that are no longer current should be updated to include a Date Ended Notes

Current.

Owner/Operator Street Number **English Name** 

Description The street number from the address of the facility owner or operator.

Data Type and Length VARCHAR2 (12) **Allowed Values** 

Any value

Not provided blank

**Default Value** blank

## **HOWNER OPERATOR5**

English Name Owner/Operator Street 1

**Description** First line of the street address or post office box number of the facility owner or operator.

Data Type and Length VARCHAR2 (30)

Allowed Values Any value

blank Not provided

**Default Value** blank

**English Name** Owner/Operator Street 2

**Description** Second line of the street address or post office box number of the facility owner or operator.

Data Type and Length VARCHAR2 (30)

Allowed Values Any value

blank Not provided

**Default Value** blank

**English Name** Owner/Operator City

**Description** The city or town in the address of the facility owner or operator.

Data Type and Length VARCHAR2 (25)

Allowed Values Any value

blank Not provided

Default Value blank

English Name Owner/Operator State

**Description** The state code in the address of the facility owner or operator.

Data Type and Length CHAR (2)

Allowed Values If Owner/Operator Country <> US or blank then State code in LU\_FOREIGN\_STATE

If Owner/Operator Country = US or blank then State postal code in LU\_STATE

blank Not provided

Default Value blank

**Notes** For a list of valid state codes, refer to the Column Information Report for LU\_STATE and LU\_FOREIGN\_STATE.

## **HOWNER\_OPERATOR5**

English Name Owner/Operator Zip Code

**Description** Zip code in the address of the owner or operator.

Data Type and Length VARCHAR2 (14)

Allowed Values Any value

blank Not provided

**Default Value** blank

English Name Owner/Operator Country

**Description** The country code in the address of the facility owner or operator.

Data Type and Length CHAR (2)

Allowed Values Country code in LU\_COUNTRY

US United States blank US (United States)

**Default Value** US

Notes For a list of valid country codes, refer to the Column Information Report for LU COUNTRY.

If Country is blank, then a value of 'US' will be assumed.

English Name Owner/Operator Telephone Number

**Description** Telephone number associated with the owner or operator.

Data Type and Length VARCHAR2 (15)
Allowed Values Any value

Any value

blank Not provided

**Default Value** blank

**Notes** Telephone number can include space, parentheses and hyphen.

English Name User ID of Last Change

**Description** Records the user ID of the last person to change the data.

Data Type and Length VARCHAR2 (6)
Allowed Values Valid user ID
Default Value Current user ID

## **HOWNER\_OPERATOR5**

English Name Date of Last Change

**Description** Records the date that the data was last changed.

Data Type and Length DATE

Allowed Values Valid date/time stamp

Default Value Current date and time

English Name Notes

**Description** Additional information regarding the owner/operator.

Data Type and Length VARCHAR2 (2000)

Allowed Values Any value

blank Not provided

**Default Value** blank

<sup>\*</sup> End of Report \*